SAMSUNG ELECTRONICS

Knox E-FOTA On-Premises

Guidance for Upgrade to DFM 1.0.1.11 from DFM 1.0.1.10

Version: 1.8

Last Update: Dec 2025

Document History

What	Ver.	When
I. Added:		
Guidance for upgrade to DFM 1.0.1.11		
← There are a couple of items that have changed:	Ver1.8	Dec 2025
1) changed Podman image files, 2) alter table, 3)New Feature: Configurable	00.2.0	200 2020
polling_interval_default run command		
I. Added:		
Guidance for upgrade to DFM 1.0.1.10		
← There are a couple of items that have changed:	Ver1.7	Apr 2025
2) changed Podman image files, 2) alter table		-
I. Added:		
Guidance for upgrade to DFM 1.0.1.9		
← There are a couple of items that have changed:	Ver1.6	Dec 2024
3) changed Podman image files, 2) New Feature: dfm mysql update and minio		
update		
I. Added:		
Guidance for upgrade to DFM 1.0.1.8		
← There are a couple of items that have changed:	Ver1.5	Jun 2024
1) changed Podman image files, 2) alter table, 3) New Feature: Configurable license	Vei 1.5	Juli 2024
app enabled, port, core run command, 4) Background app setting		
I. Added:		
Guidance for upgrade to DFM 1.0.1.7	Ver1.4	Oct 2023
← There are a couple of items that have changed:	Ver1.4	OCI 2023
1) changed Docker image files, 2) New Feature: Configurable device group polling		
I. Added:		
Guidance for upgrade to DFM 1.0.1.6		
← There are a couple of items that have changed:	Ver1.3	Apr 2023
1) changed Docker image files, 2) alter table, 3) New Feature: Configurable Device		
Group polling		
I. Added:		
Guidance for upgrade to DFM 1.0.1.5		
← There are a couple of items that have changed:	Ver1.2	Jul 2022
1) changed Podman image files		
I. Added:		
Guidance for upgrade to DFM 1.0.1.4		
← There are a couple of items that have changed:	Ver1.1	Mar 2022
1) changed Podman image files, 2), New Feature: Configurable length of password		
digits		
I. Added:		
Guidance for upgrade to DFM 1.0.1.3		
← There are a couple of items that have changed:	Ver1.0	Jan 2022
1) changed Podman image files		
-		

[ADDENDUM] : Upgrade from 1.0.1.10 to 1.0.1.11

1.1. Purpose of this document

The purpose of this document is to provide instructions to <u>upgrade a system with DFM 1.0.1.10 to</u> <u>1.0.1.11</u>. If DFM has never been installed on the server, please refer to the server installation guides.

1.2. Why patch DFM Podman images, etc.?

- Updated bug issues
- New feature: changed podman image dfm-core and dfm-console

1.3. What changed in version 1.0.1.11?

	Category	Summary
1	Podman image	- dfm-core image - dfm-console image

- 1. Changed two Podman image files when compared with the previous DFM 1.0.1.11 version:
 - dfm-core
 - dfm-console

1.4. Update the DFM Module

During the update, a short circuit may occur.

The DFM Module is logged in with a **dedicated service account** and operates with the privileges of the account. You should log in with the account you used to install before.

1.4.1. Install v1.0.1.11 DFM Module Package

The following command shows you how to install the v1.0.1.11 tar compress package:

```
1) delete exist dfm folder
rm -rf /tmp/sec-dfm_1.0.1.11/dfm

2) extract package
tar -zxvf sec-dfm_1.0.1.11.tar.gz -C /tmp

example)
$ tar -zxvf sec-dfm_1.0.1.11.tar.gz
/tmp/sec-dfm_1.0.1.11/dfm/
....
/tmp/sec-dfm_1.0.1.11/dfm/usr/
/tmp/sec-dfm_1.0.1.11/dfm/usr/bin/
/tmp/sec-dfm_1.0.1.11/dfm/usr/bin/dfm
```

1.4.2. Alter Table

1) Alter table using an SQL script

```
1) Executing an SQL script podman exec -i dfm-mysql mysql -uroot -p[password] < /tmp/sec-dfm_1.0.1.11/dfm/mysql-query/patch_1.0.1.11.sql
```

1.4.3. DFM CLI Update

[STEP 1] Copy the DFM CLI.

sudo cp /tmp/sec-dfm_1.0.1.11/dfm/bin/dfm /usr/local/bin or sudo cp /tmp/sec-dfm 1.0.1.11/dfm/bin/dfm /usr/bin

Example)

sudo cp /tmp/sec-dfm_1.0.1.11/dfm/bin/dfm /usr/local/bin

Is -al /usr/local/bin/dfm or Is -al /usr/bin/dfm

-rwxr-xr-x. 1 efotadm efotadm 2902624 Mar 2 07:42 dfm

dfm version

version: 1.0.11 Red Hat Enterprise Linux release 8.4 (Ootpa)

[STEP 2] Check the DFM CLI privileges and version.

1.4.4. Configure polling interval default

(STEP 1) Check the DFM CLI version.

dfm version version: 1.0.11

[STEP 2] Set the polling interval default second (sudo is required in root mode.)

If you enter an empty value in second, it is set automatically.

Example)

#root mode

sudo dfm config set polling_interval_default=

#rootless mode

dfm config set polling_interval_default=

[STEP 3] Set the polling interval default second (Allowed values: integer type).

Example)

dfm config set polling_interval_default=86400

【STEP 4】 Confirm the configurations.

dfm config get polling_interval_default

1.4.5. DFM Core Update

The released **Core** image information is as follows:

[STEP01] Stop the running core server.

#root mode

sudo dfm terminate dfm-core

#rootless mode

dfm terminate dfm-core

(STEP02) Load the released podman image.

```
#root mode
sudo podman load -i /tmp/sec-dfm_1.0.1.11/dfm/images/dfm-core_1.0.1.11.tar

#rootless mode
podman load -i /tmp/sec-dfm_1.0.1.11/dfm/images/dfm-core_1.0.1.11.tar
```

[STEP03] Change repository and tag's configuration

```
dfm config set core_img_rep=localhost/dfm-core

dfm config set core_img_tag=1.0.1.11
```

[STEP04] Confirm the changed repository and tag's configuration

```
dfm config get core_img_rep
dfm config get core_img_tag
```

(STEP05) Start up Server

DFM Core Server

#rootless mode
dfm start dfm-core
#root mode

sudo dfm start dfm-core

If it is redhat 8.4 version, run health check

[Validation]

Make sure the DFM Core Server container is in a healthy state. It may take some time until its state is healthy.

```
podman healthcheck run dfm-core

#rootless mode
podman ps -a

#root mode
sudo podman ps -a
```

Example)

CONTAINER ID	IMAGE	STATUS	NAMES
9baaf3c0338a	localhost/mysql:8.0.36	Up 36 seconds ago (healthy)	dfm-mysql
77d1f27b3038	localhost/minio/minio:RELEASE.2022-	Up 38 seconds ago	dfm-minio
	04-30T22-23-53Z	(healthy)	
15dd23fb2355	localhost/dfm-core:1.0.1.11	Up 32 seconds ago	dfm-core
		(healthy)	

1.4.6 DFM Admin Console Update

The released **Admin Console** image information is as follows:

[STEP01] Stop the running console server.

#root mode sudo dfm terminate dfm-console #rootless mode dfm terminate dfm-console

[STEP02] Load the released podman image.

```
#root mode
sudo podman load –i /tmp/sec-dfm_1.0.1.11/dfm/images/dfm-console_1.0.1.11.tar

#rootless mode
podman load -i /tmp/sec-dfm_1.0.1.11/dfm/images/dfm-console_1.0.1.11.tar
```

[STEP03] Change repository and tag's configuration

```
dfm config set console_img_rep=localhost/dfm-console

dfm config set console_img_tag=1.0.1.11
```

(STEP04) Confirm the changed repository and tag's configuration

```
dfm config get console_img_rep
dfm config get console_img_tag
```

【STEP05】 Start up Server

DFM Core Server

#rootless mode dfm start dfm-console

#root mode

sudo dfm start dfm-console

[Validation]

Make sure the DFM Core Server container is in a healthy state. It may take some time until its state is healthy.

```
# If it is redhat 8.4 version, run health check podman healthcheck run dfm-console

#rootless mode
podman ps -a

#root mode
sudo podman ps -a
```

Example)

CONTAINER ID	IMAGE	STATUS	NAMES
9baaf3c0338a	localhost/mysql:8.0.36	Up 36 seconds ago (healthy)	dfm-mysql
77d1f27b3038	localhost/minio/minio:RELEASE.2022-	Up 38 seconds ago (healthy)	dfm-minio
	04-30T22-23-53Z		
15dd23fb2355	localhost/dfm-core:1.0.1.11	Up 32 seconds ago (healthy)	dfm-core
c49a291fbede	localhost/dfm-console:1.0.1.11	Up 32 seconds ago (healthy)	dfm-console

< EOF (End Of File) >